

ASUS RT-AC88U

Powered by
Asuswrt-Merlin

Logout

Reboot

English

Quick Internet Setup

Operation Mode: [wireless router](#) Firmware Version: [384.18](#)
SSID: [Traditions_2G](#) [Traditions_5G](#)

VPN Status VPN Server VPN Client TOR

General

Network Map

Guest Network

AiProtection

Adaptive QoS

Traffic Analyzer

Game

Open NAT

USB Application

AiCloud 2.0

Tools

Advanced Settings

Wireless

LAN

WAN

Alexa & IFTTT

IPv6

VPN

Firewall

Administration

System Log

Network Tools

OpenVPN Client Settings

OpenVPN PPTP/L2TP

Before starting the service make sure you properly configure it, including the required keys, otherwise you will be unable to turn it on.

In case of problem, see the [System Log](#) for any error message related to openvpn.

Client control

Select client instance1: NaplesStore

Service stateON

Automatic start at boot time☒ Yes ☐ No

DescriptionNaplesStore

Import .ovpn fileBrowse... No file selected. Upload

Network Settings

Interface TypeTUN

ProtocolTCP

Server Address and PortAddress: Traditions-Naples.chickenkiller.c Port: 1194

Accept DNS ConfigurationRelaxed

Create NAT on tunnel☐ Yes ☒ No Routes must be configured manually.

Inbound Firewall☐ Block ☒ Allow

Authentication Settings

Authorization ModeTLS

Username/Password Authentication☒ Yes ☐ No

UsernameTraditionsMpls

Password..... Show password

Username / Password Auth. Only☐ Yes ☒ No

Crypto Settings

Keys and CertificatesEdit...





Cipher NegotiationEnable (with fallback)

Negotiable ciphersCHACHA20-POLY1305:AES-128-GCM:AES-256-GCM:AES-12

Legacy/fallback cipherDefault

TLS control channel security (tls-auth / tls-crypt)Disabled

Auth digestDefault

Advanced Settings				
Log verbosity (0-6, default=3)	<input type="text" value="3"/>			
Compression	Disabled ▾			
TLS Renegotiation Time (in seconds, -1 for default)	<input type="text" value="-1"/>			
Connection Retry attempts (-1 for infinite)	<input type="text" value="-1"/>			
Verify Server Certificate Name	No ▾			
Force Internet traffic through tunnel	Policy Rules (strict) ▾			
Block routed clients if tunnel goes down	<input type="radio"/> Yes <input checked="" type="radio"/> No			
Rules for routing client traffic through the tunnel (Max Limit : 100)				
Description	Source IP	Destination IP	Iface	Add / Delete
<input type="text"/>	<input type="text"/>	<input type="text"/>	VPN ▾	
134 Subnet		192.168.134.0/24	VPN	
135 Subnet		192.168.135.0/24	VPN	
NaplesCable		10.0.4.0/24	VPN	
Custom Configuration				
<pre>resolv-retry infinite float keepalive 15 60 remote-cert-tls server</pre>				
Default		Apply		

[Help & Support](#) [Manual](#) | [Utility](#) | [Product Registration](#) | [App](#)

FAQ

2020 ASUSTeK Computer Inc. All rights reserved.